

UY000001 / UY000002 importing of new tool

If the parabolic mirror VY000024 or the gooseneck VY000020 / VY000021 has been ordered separately, the application data for the device must be loaded into the UY000001 / UY000002 first.

Data are supplied via USB-stick and stored in the directory //DEV00004/Tools/ as XML-File.

The tools can be integrated via the menu „Import new Tool“.

- Home → Export/Import → “Import new Tool”
- Select storage location “USB”
- Depending on the tool, select one of the following files
 - Parabol_xxxxxxx.xml
 - Schwanenhals_xxxxxxx.xml
- Confirm with “OK” and then with “Yes”.

